NSIM ensim'





Ensim Pro 10.3.0 for Linux Customization Guide

Published: 25 April 2007

This document contains information proprietary to Ensim Corporation and its receipt or possession does not convey any rights to reproduce, disclose, manufacture, or sell anything it might describe. Reproduction, disclosure, or use without Ensim's specific written authorization is strictly forbidden. Ensim Corporation makes no representations or warranties with respect to the contents or use of this document. It also reserves the right to revise this publication and make changes to the content at any time, without the obligation to notify any person or entity of such revisions or changes.

Further, Ensim Corporation assumes no responsibility or liability for any errors or inaccuracies, makes no warranty of any kind (express, implied or statutory) with respect to the contents or use of the information, and expressly disclaims any and all warranties of merchantability, fitness for particular purposes, and non-infringement of third party rights.

Ensim and the Ensim logo are registered trademarks of Ensim Corporation. All other trademarks are the property of their respective owners.

© 2007 Ensim Corporation. All rights reserved.

CORPORATE HEADQUARTERS

ENSIM CORPORATION 3945 Freedom Circle, Suite 1100 Santa Clara, California 95054 (408) 496-3700

www.ensim.com

Contents

About this guide 5		
Introduction	5	
Intended audience and required skills	5	
Document conventions		
Support and feedback	6	
Chapter 1 Overview of customizations	7	
Introduction	7	
About resource customization	7	
Identifying resources	7	
Resource stores		
Why do we need resource stores	9	
About branding control panels	11	
Guidelines for customization	11	
User interface terminology	12	
Chapter 2 About the resource customization tool	14	
Introduction		
About the resource customization tool	14	
Command line options	14	
Resource operations		
Operation 'list'		
Operation 'download'		
Operation 'customize'		
Operation 'revert'		
-		
Chapter 3 Customizing a skin	20	
• •		
Introduction		
Creating a skin		
Customizing a skin		
Adding links to the left navigation bar		
Adding links in the shortcuts area		
Relocating shortcuts sections		
Regrouping the shortcuts matrix		
Customizing the font and color palette		
Customizing icons		
Relocating information panels on the left navigation bar		
Miscellaneous customizations		

Appendix A List of referenced images

About this guide

Introduction

This guide provides instructions for customizing Ensim® Pro 10.3.0 for Linux®. Ensim Pro is a robust control panel solution for small and large professional hosting providers that runs on a Linux server running any of the following operating systems— FC 6 (Fedora[®] Core 6), FC 4, FC 2, CentOS 4.4 (Community Enterprise Operating System 4.4), and RHEL 4 (Red Hat® Enterprise Linux ES Release 4). For simplicity, Ensim Pro 10.3.0 for Linux is referred to as "Ensim Pro" throughout the document.

Intended audience and required skills

This guide is intended for those who want to customize the look and feel of Ensim Pro. To use this document, you need to be proficient in HTML, CSS, XSL, and XML. You also need to be familiar with the Linux platform.

Document conventions

Throughout this guide, specific fonts are used to identify user input, computer code, and user interface elements. The following table lists conventions used in this guide.

Convention	How it is used
Bold text, serif font	Used for information you type as well as for file names, path names, and CD names.
	Example: On the command line, type continue.
Italic text	Used for column names, field names, window names, and book titles.
	Example: The Select Installation Folder window is displayed.
Bold, italic text enclosed in	Used for variables you replace with the appropriate information.
angle brackets	<i>Example:</i> Type < <i>server_name</i> > where < <i>server_name</i> > is the IP address or host name of your server.

Table 1. Docume	nt conventions
-----------------	----------------

Convention	How it is used
Bold text, sans serif font	Used for items you click or press, such as buttons, menus, and command keys.
	Example: Click Start > Settings > Control Panel.
Non-proportional font	Used for system messages, screen text, and code examples.
	Example: The following message is displayed:
	The server has been added.

Note: In addition, key information is sometimes displayed using special headings and formats, such as this one, to make it stand out from regular text.

Support and feedback

For Ensim online support or feedback, use the following links:

- http://support.ensim.com to create an Ensim Support account and access other documentation
- https://onlinesupport.ensim.com to log in to Ensim Support using an existing account
- http://onlinesupport.ensim.com/kb_search.asp?product=lwp to search the knowledge base
- http://www.ensim.com/about/feedback.asp to provide feedback to Ensim

Note: All customers receive passwords that allow access to the Ensim Support site. If you do not have a password, contact your organization's liaison to Ensim.

Overview of customizations

Introduction

This section introduces the concepts and terminologies used to explain customization.

7
9
11
11
12

About resource customization

A resource is a customizable unit that can be broadly classified into two types—dynamic and static. A dynamic resource is a resource that resolves to application code and executes dynamically on the server. For example, when you log into Ensim Pro control panel and click on the option **List Sites**, the action executes application code to obtain the required result.

A static resource is a resource that resolves to a static file on the server, for example, an image displayed in Ensim Pro is a static resource as it resolves to a static image file on the server. *This document explains static resource customization*.

Identifying resources

The customizations described in this document refer to static resource customizations. To easily distinguish a static resource from a dynamic resource, look for the keyword **/static/** in the Web URL of the page. For example, the URL of an image reads as follows:

https://<*server_name*>/static/images/sites.gif. Every static resource in Ensim Pro is identified by the keyword /static/ in the Web URL.

Types of resources

The static resources of Ensim Pro are organized according to the type of the resource to which they belong. There are 5 types of static resources in Ensim Pro.

The static resources are:

- XML files (*Short name:* xml). XML files contain information that specify the position of links on the left and top navigation bars, the dashboard, the shortcuts, and the top information panel at different administrative levels.
- XSL stylesheets (*Short name:* xsl). XSL stylesheets are files that define the layouts of the top information panel, the left and top navigation bars, the shortcuts, and the dashboard at different administrative levels.
- **JavaScript files** (*Short name:* js). JavaScript files are files that perform client-side parameter validation and render the contents of flip lists.
- **Image files** (*Short name:* images). Image files are icons of different types, such as *.gif*, *.jpeg*, *.png*, displayed in the control panel.
- **HTML stylesheets** (*Short name:* css). HTML stylesheets are files that define the visual appearance of the control panel.

The following illustration shows the file structure of the customizable resources.




Figure 1. File structure of resources

Ease of customization

Earlier versions of Ensim Pro required technical proficiency in python and familiarity with the application logic to perform customizations. Ensim Pro has now revamped its application framework to segregate the presentation layer from the application logic. This design philosophy brings a whole new array of possibilities to Ensim Pro customization besides making it more accessible and straightforward. You can now customize any section of the control panel with minimal effort.

The skins use CSS and XSL style sheets to transform XML content and generate an HTML Web page. To customize the control panel, you need to have a working knowledge of HTML, CSS, XSL, XML, and JavaScript. Whenever you customize, you simply make a custom copy of the file you want to customize using the customization tool, then make the changes to your custom file. This ensures that you can reload the default settings, at any time, if necessary.

Resource stores

Resource stores classify customizable resources according to the nature and scope of customization.

Why do we need resource stores

Ensim Pro offers a suite of 3 skins—*Cocoon, Mercury*, and *Classic*. In addition, Server Administrators, Reseller Administrators, and Site Administrators can choose to create or customize their control panel and extend this suite. Many of the resources used by skins are common across all skins and do not need to be customized for each skin. For the sake of efficiency, these resources are not duplicated for each skin. For instance, the JavaScript file **validate.js** performs client-side parameter validation and is common across all skins because it does not affect the visual configuration of a skin.

On the other hand, there are resources that are different for each skin, because they affect its visual configuration. These resources define the look and feel of that particular skin and are therefore skin-specific. For example, the HTML stylesheet **isp.global.css**, which defines the look and feel of the Server Administrator control panel is a skin-specific file.

To delineate these resources according to the scope and impact of their customizations, Ensim Pro introduces the concept of **resource stores**.

Types of resource stores

Ensim Pro provides the following resource stores:

- **Default store.** This store contains resources that are used in common by all the skins on Ensim Pro. Typically, these resources are XML files and JavaScript files and do not affect the visual appearance of the control panel. Ensim Pro has only one Default store located at /usr/lib/ensim/frontend/static/.
- Skin stores. This store contains various types of resources that combine to define the look and feel of the control panel. The resources for each skin are stored in independent skin stores since the look and feel of the control panel varies according to the skin. The customizations made to the resources in this store are visible to all users.

For example, the Cocoon skin stores its resources in its own skin store *Cocoon*, while the Mercury skin stores its resources in its skin store *Mercury*. The Skin store is located at /usr/lib/ensim/frontend/skins/*<skin_name>*/.

Cocoon: /usr/lib/ensim/frontend/skins/cocoon/

Mercury: /usr/lib/ensim/frontend/skins/mercury/

Classic: /usr/lib/ensim/frontend/skins/classic/

• User stores. Ensim Pro enables Server Administrators, Reseller Administrators, and Site Administrators to customize the control panel according to their preferences. For more information, see the section on branding ("About branding control panels" on page 11).

Whenever a Server Administrator, Reseller, or Site Administrator customizes a resource, that resource is placed in the corresponding user store. For example, customizations made by a Server Administrator are placed in the Server Administrator store. The customizations made to resources in a user store are visible only to that particular user. Ensim Pro supports the following types of User stores:

• Server Administrator store. This store contains resources that are customized by the Server Administrator.

Path: /etc/appliance/customization/stores/isp/

• **Reseller Administrator store.** This store contains resources that are customized by Reseller Administrators. Resellers can have their own independent customized stores.

Path: /etc/appliance/customization/stores/reseller/<reseller_name>

• Site Administrator store. This store contains resources that are customized by Site Administrators. Site Administrators can have their own independent customized stores.

Path: /etc/appliance/customization/stores/site/<site_name>

Note: User Administrators do not have their own customized store. They inherit the store attributes of their Site Administrator. Therefore, the resource store of a User Administrator is /etc/appliance/customization/stores/site/<site_name>.

Selecting a resource store for customization

When you customize a resource, you need to select the store whose resources you want to customize. Once you customize, you must place your customized resources in that store.

- **Default store.** This store contains the required resources in Ensim Pro. Do not customize resources in this store.
- **Skin store**. This store contains resources specific to a skin that are visible to all users. Use this store to perform customizations that are common and need to be visible across administrative levels.
- **User store.** This store contains resources specific to the user customizing the control panel. Use this store to perform customizations that are specific or local to a particular administrative level.

Displaying resources in Ensim Pro

When Ensim Pro displays a resource (such as a .gif, .css, .js, or .xsl) on the control panel, it searches for the resource in the following stores in the order given below:

- User store
- Skin store
- Default store

The resource to be displayed is selected from the first store that contains that particular resource. If there is no customized resource available, then the resource is selected from the Default store. If a resource has been customized, then it is fetched from the User store (of the user logged in) or the Skin store. If the resource does not exist in any store, the error Page Not Found is displayed.

About branding control panels

You can customize the look and feel of Ensim Pro to suit your preferences or extend your company's branding to convey brand association and unity. This look and feel includes micro-level customizations on an existing skin such as logo, banner, colors, graphics, menu configuration, and styles or using a completely new visual style in the form of a new skin.

What you can change: Banners and logos, colors and graphics, padding, spacing, and font sizing, display and position of menu options on the left navigation bar, top navigation bar, shortcuts, and content (service providers can add content to the Site Administrator control panel).

What you cannot change: The title of the page displayed in the browser window.

Your customers cannot change the branding of their top-level control panels. However, the system is designed so that they can override your settings and customize the control panels used by their customers (their Reseller Administrators, Site Administrators and User Administrators).

Your branding preferences are automatically applied to reseller, site, and user control panels only if resellers and Site Administrators have not added their own branding preferences. This preserves their ability to brand their customers' control panels.

When you add or change your branding preferences, those preferences are applied as follows:

Control panel	How preferences are applied
Resellers and sites you own	Your changes are always applied immediately.
Resellers and sites owned by your resellers	Your changes are applied only if the reseller has not customized the reseller or site control panels.
Users added by Site Administrators	Changes are applied only if the Site Administrator or reseller has not customized the user control panel.

Table 2. Application of branding preferences

Guidelines for customization

Ensure that you observe these guidelines when you customize the control panel.

- First, identify the file path that refers to the resource (CSS, XSL, JS, XML, or images) you want to customize. If it includes the keyword /static/ after the server name, you can customize it. For example, if you want to customize an image, right-click on the image, select Properties and observe the URL, it will read: https://<server_name>/static/images/sites.gif. All customizable resources begin with /static/. Next, identify the relative path, that is the path that follows the keyword /static/. For example, the relative path in the above example is images/sites.gif.
- Copy the original resource to a new folder and then modify the resource. In case of image files, you can directly copy the files to the new location.
- When you customize images, ensure that the new image is saved using the name of the file you want to replace. Also, make sure that you preserve the dimensions of the original image for better results.

• When you customize an XML document, run the **xmlint** command as follows to ensure there are no parsing errors due to mismatched tags.

xmllint --noout /etc/appliance/admin/skins/<skin_name>/xsl/isp.navbar.xsl

If there are parsing errors, the command displays the errors; if there are no errors, no output is displayed.

Important: Ensim Pro does not revert to the default XSL or XML files if the customized files cannot be parsed.

User interface terminology

The following section uses graphics to convey the terminology used to identify the different customizable components of the Ensim Pro interface. The style sheets and other customizable resources use the terminology in their file names and class names. Acquainting yourself with the terminology helps in easy identification of the files and classes that you need to modify.

- Top bar. Identifies the top display panel
- Dashboard. Identifies the shortcuts section
- Navbar. Identifies the left navigation bar
- Subnav bar. Identifies the top navigation bar
- Flip list. Identifies the lists that can be sorted into ascending or descending order
- Form. Identifies the forms that require inputs

0

The following figures illustrate the terminology used to identify the customizable components of Ensim Pro.



ensim	T	op Bar		Constant Con	r Statistics 25% General 2555 - 654% Deced
gis toto	Last later, Contribute, Add to-Masser 1, Said	4	— Sı	ibnav Ba	ur 🔤
Server Administrator	Gite List				
		Sheet D	w 3		Tranh Sho-A
os KML	Nite	Ratus	Tree	12.Address	Actions
ETE MALIAJEA	mensiam	Flip List	10	18.76.8.179	
Navbar	then.ent	•	10	10.76-8.170	12111
02525260 HER-102526	Rooman (co-leika monta)		10	10.76-8.370	2282
EMARL PTP	imita.com		10	10.76.8.170	
DNS CHER TOTALE	10 Meres per page				K 4 9 1
IPOPTERPORT SHIFTAURATION					
EUP.					
Earin Pu12.0.0-000413.6.4	************************************				



Figure 2. Terminology

About the resource customization tool

Introduction

In this section:	
About the resource customization tool	14
Resource operations	18

About the resource customization tool

The resource customization tool is a command line tool used for customizing resources. Using the tool, you can view the list of customizable resources, customize them, and revert customized resources to their default configuration.

Command line options

The following table lists the commands you can use for various operations.

Command	Options	Optional/Required
GUIResourceList	The supported options are: -h,help Displays the help message	Optional
	 role=<<i>ROLE</i>> Role of the administrator performing the action. For example: Server Administrator:role=isp Reseller Administrator: role=reseller 	Required
	 Site Administartor:role=siteadmin 	

Δ

Command	Options	Optional/Required
	 user=USER This specifies the user name. If you are an ISP or a reseller, then USER is your log in name. If you are a site administrator, then the log in name is username>@<domainname.com>.</domainname.com> 	Required
	skin=SKIN This specifies the skin name that is to be used. [cocoon mercury classic] The default skin is cocoon.	Optional
	url=URL The relative URL of the resource that needs to be listed. This should begin with /static/.	Optional
GUIResourceDownload	The supported options are: -h,help Displays the help message	Optional
	 role=<<i>ROLE</i>> Role of the administrator performing the action. For example: Server Administrator:role=isp Reseller Administrator: role=reseller Site Administartor:role=siteadmin 	Required
	user=USER This specifies the user name. If you are an ISP or a reseller, then USER is your log in name. If you are a site administrator, then the log in name is: <username>@<domainname.com>.</domainname.com></username>	Required
	skin=SKIN This specifies the skin name that is to be used. [cocoon mercury classic] The default skin is cocoon.	Optional

Δ

Command	Options	Optional/Required	
	url=URL The relative URL of the resource that needs to be downloaded. This should begin with /static/.	Required	
	The supported options are: -h,help Displays the help message	Optional	
	 role=<<i>ROLE</i>> Role of the administrator performing the action. For example: Server Administrator:role=isp Reseller Administrator:role=siteadmin Site Administrator:role=siteadmin 	Required	
	user=USER This specifies the user name. If you are an ISP or a reseller, then USER is your log in name. If you are a site administrator, then the log in name is: <username>@<domainname.com>.</domainname.com></username>	Required	
	skin=SKIN This specifies the skin name that is to be used. [cocoon mercury classic] The default skin is cocoon.	Optional	
	url=URL The relative URL of the resource that needs to be customized. This should begin with /static/.	Required	

Δ

Command	Options	Optional/Required	
	 uri=URI This local resource to be used for customizing the URL. This parameter can be specified in the standard URI syntax, which means that any of the following are valid arguments for this option: /tmp/logo.gif , file:///tmp/logo.gif http://mywebsite.com/logo.gif ftp://myuser:password@mysite.com/log o.gif	Required	
GUIResourceRevert	The supported options are: -h,help Displays the help message	Optional	
	 role=<<i>ROLE</i>> Role of the administrator performing the action. For example: Server Administrator:role=isp Reseller Administrator: role=reseller Site Administartor:role=siteadmin 	Required	
	user=USER This specifies the user name. If you are an ISP or a reseller, then USER is your log in name. If you are a site administrator, then the log in name is: <username>@<domainname.com>.</domainname.com></username>	Required	
	skin=SKIN This specifies the skin name that is to be used. [cocoon mercury classic] The default skin is cocoon.	Optional	
	url=URL The relative URL of the resource that needs to be reverted back. This should begin with /static/.	Optional	

ABOUT THE RESOURCE CUSTOMIZATION TOOL • CHAPTER 2

Resource operations

The tool supports the following operations.

- Operation 'list' (page 18)
- Operation 'download' (page 18)
- Operation 'customize' (page 18)
- Operation 'revert' (page 19)

Operation 'list'

The list operation is used to view the resources available for customization along with information on the store to which they belong. If no particular resource is specified (using the --**url** option), all the available resources are listed, otherwise, only information about the specified resource is displayed. If you do not specify the skin (using the --**skin** option) for which you want to view resources, only resources from the Default and Common stores are listed; otherwise, the list also includes resources available within the specified skin store.

Operation 'download'

The download operation is used to download the resource specified by the **-url** option. You can redirect the output of the download operation to a local file using the redirection (>) operator.

When you want to customize a resource, you first make a local copy of the original resource from one of the stores. The download operation is used to download the resource (you want to customize) into a local file. To download, specify the name of the resource using the --**url** option.

As in the list operation, if you specify a skin using the **-s** option, then the resource is downloaded from that particular skin store; if you do not specify a skin, the resource is downloaded from the Default/Common stores, if they exist.

Operation 'customize'

The customize operation uploads the resource specified with the --**uri** option to the control panel. After you upload, this resource is available and can be accessed through the path or URL specified with the --**url** option. The uploaded resource is placed in the Customized Store. The resource you want to upload can point to a local file, or any remote location, the specification of which must meet the standard URI syntax.

You must ensure that the type of the resource being uploaded exactly matches the type of the resource that is being replaced (customized). For example, if you customize (--**url option**) an image resource of type .gif, the resource you upload (--**uri** option) must also be an image resource of type .gif, preferably with the same dimensions (height and width). Similarly, if you customize an XML file, the file you upload must also be an XML file, and furthermore, it must also be an XML file that is of the same format as the XML file being customized. The best way to customize non-binary resources such as XML files, is to first download the resource to a local file, make the necessary modifications, and then use the customize operation to upload the resource.

Note: Since Ensim Pro supports resource customization on a per-skin basis, you must specify a skin using the --**skin** option.

Operation 'revert'

The revert operation is used to revert customized resources to their default settings.

You must specify the resource for which you want to undo customization (using the --**url** option) and the skin for which the resource was customized (using the --**skin** option).

CHAPTER 3

Customizing a skin

Introduction

This section describes how to create a skin and customize its resources as a Server Administrator using the *Skin* store. Since the customizations use the *Skin* store, they will be visible to all administrative levels. You may similarly experiment with other stores, such as the User store, depending on your customization requirements. Before you proceed, review the overview section ("Overview of customizations" on page 7) and the section on the customization tool ("User interface terminology" on page 12).

Note: To perform any operation, you must log in to the Ensim Pro server as a root user.

In this section:

Creating a skin	20
Customizing a skin	21

Creating a skin

The easiest way to create a new skin is to copy the skin directory of an available skin to a new directory as described in the following procedure.

▼ To create a skin:

- 1 Log in to the Ensim Pro server as the root user.
- 2 Change to the directory /usr/lib/ensim/frontend/skins/.

cd /usr/lib/ensim/frontend/skins/

3 Copy the contents of an existing skin directory recursively into a new directory. Further, preserve the existing file permissions (using the **-p** option).

cp -Rp <old_skin_dir>/ <new_skin_dir>

For example, to copy the existing skin directory *cocoon* to a new directory *myskin*, type the following command:

cp -Rp cocoon/ myskin

A new directory, *myskin*, is created under the directory **/usr/lib/ensim/frontend/skins/**, hence, *myskin* is recognized as a new skin by the Ensim Pro control panel. The control panel displays the name of the skin directory as a new skin option in the control panel. To apply the new skin to your control panel, log in to the Server Administrator control panel, and choose *myskin*. Notice that the new skin assumes the look and feel of the skin you copied. Customize the skin components as described in the customization instructions ("Customizing a skin" on page 21) to provide a distinct look and feel for the new skin.

Customizing a skin

This section explains how to customize a skin.

Note: Some of the images used to illustrate the customizations exceed standard	
dimensions. These images are displayed in landscape mode in a separate sec	tion
("List of referenced images" on page 28).	

You can customize a skin by:

Adding links to the left navigation bar	21
Adding links in the shortcuts area	
Relocating shortcuts sections	
Regrouping the shortcuts matrix	23
Customizing the font and color palette	
Customizing icons	
Relocating information panels on the left navigation bar	
Miscellaneous customizations	

Adding links to the left navigation bar

The following procedure explains how to add a link, such as **Contact Us**, next to the **Services** option on the left navigation bar of the Server Administrator control panel.

▼ To add a custom link to the left navigation bar:

- 1 Log in to the Ensim Pro server as the root user.
- 2 Verify that the resource /static/xml/isp.navbar.xml exists.

/usr/bin/ensim/GUIResourceList --role *<role>* --user *<username>* --url /static/xml/isp.navbar.xml --skin *<skin_name>*

3 Download the resource.

/usr/bin/ensim/GUIResourceDownload --role <*role*> --user <*username*> --url /static/xml/isp.navbar.xml --skin <*skin_name*> > /tmp/isp.navbar.xml

- 4 Make the required changes to the file /tmp/isp.navbar.xml. Search for the <item> nodes, add nodes according to your requirement, and save your changes. For example, to insert a link Contact Us, next to the link Services, insert the Contact Us XML snippet as shown in the navigation bar links illustration ("Adding links to the left navigation bar" on page 28).
- **5** Upload the resource to the Ensim Pro server.

/usr/bin/ensim/GUIResourceCustomize --role *<role>* --user *<username>* --url /static/xml/isp.navbar.xml --skin *<skin_name>*--uri /tmp/isp.navbar.xml The resource is customized. To verify the result, log in to the Server Administrator control panel and refresh the Web page.

If you want to revert your changes, type the following command.

/usr/bin/ensim/GUIResourceRevert --role <*role*> --user <*username*> --url /static/xml/isp.navbar.xml --skin <*skin_name*>

Adding links in the shortcuts area

The following procedure explains how to add a link, such as **Weekly Usage Reports**, next to the **Usage Reports** option (*Reports* section) in the shortcuts area of the Server Administrator control panel.

To add a custom link in the shortcuts area:

- 1 Log in to the Ensim Pro server as the root user.
- 2 Verify that the resource /static/xml/isp.dashboard.xml exists.

/usr/bin/ensim/GUIResourceList --role *<role>* --user *<username>* --url /static/xml/isp.dashboard.xml --skin *<skin_name>*

3 Download the resource.

/usr/bin/ensim/GUIResourceDownload --role *<role>* --user *<username>* --url /static/xml/isp.dashboard.xml --skin *<skin_name>* > /tmp/isp.dashboard.xml

- 4 Make the required changes to the file /tmp/isp.dashboard.xml, and save your changes. For example, to add a link Weekly Usage Reports, next to the Usage Reports option (*Reports* section), insert the Weekly Usage Reports XML snippet as shown in the shortcut area links illustration ("Adding links in the shorcuts area" on page 29).
- 5 Upload the resource to the Ensim Pro server.

/usr/bin/ensim/GUIResourceCustomize --role <*role*> --user <*username*> --url /static/xml/isp.dashboard.xml --skin <*skin_name*>--uri /tmp/isp.dashboard.xml

The resource is customized. To verify the result, log in to the Server Administrator control panel and refresh the Web page.

If you want to revert your changes, type the following command.

/usr/bin/ensim/GUIResourceRevert --role *<role>* --user *<username>* --url /static/xml/isp.dashboard.xml --skin *<skin_name>*

Relocating shortcuts sections

You can regroup or relocate the sections in the shortcuts matrix as required. The following procedure explains how to swap the locations of the **Sites** and **Reports** sections in the shortcuts area.

To relocate shortcuts sections:

- 1 Log in to the Ensim Pro server as the root user.
- 2 Verify that the resource /static/xml/isp.dashboard.xml exists.

/usr/bin/ensim/GUIResourceList --role *<role>* --user *<username>* --url /static/xml/isp.dashboard.xml --skin *<skin_name>*

3 Download the resource.

/usr/bin/ensim/GUIResourceDownload --role <*role*> --user <*username*> --url /static/xml/isp.dashboard.xml --skin <*skin_name*> > /tmp/isp.dashboard.xml

- 4 Make the required changes to the file /tmp/isp.dashboard.xml. For example, to swap the Sites and Reports sections, locate the XML snippets for the Sites and Reports sections, swap them as shown in the relocating shortcuts illustration ("Relocating shortcuts sections" on page 30). Save your changes.
- **5** Upload the resource to the Ensim Pro server.

/usr/bin/ensim/GUIResourceCustomize --role *<role>* --user *<username>* --url /static/xml/isp.dashboard.xml --skin *<skin_name>*--uri /tmp/isp.dashboard.xml

The resource is customized. To verify the results, log in to the Server Administrator control panel and refresh the Web page.

If you want to revert your changes, type the following command.

/usr/bin/ensim/GUIResourceRevert --role *<role>* --user *<username>* --url /static/xml/isp.dashboard.xml --skin *<skin_name>*

Regrouping the shortcuts matrix

By default, the cocoon skin displays the sections in the shortcuts area as a 3 X 3 matrix. You can regroup the sections to display it as a 2 X 3 or 2 X 2 matrix.

▼ To regroup the shortcuts matrix:


- 1 Log in to the Ensim Pro server as the root user.
- 2 Verify that the resource /static/xml/isp.dashboard.xml exists.

/usr/bin/ensim/GUIResourceList --role *<role>* --user *<username>* --url /static/xml/isp.dashboard.xml --skin *<skin_name>*

3 Download the resource.

/usr/bin/ensim/GUIResourceDownload --role <*role*> --user <*username*> --url /static/xml/isp.dashboard.xml --skin <*skin_name*> > /tmp/isp.dashboard.xml

4 Make the required changes to the file /tmp/isp.dashboard.xml. For example, to regroup the shortcuts sections into a 3 X 3 matrix, update the value of the attribute <columns>3</columns> as shown in the following figure, and save your changes.





5 Upload the resource to the Ensim Pro server.

/usr/bin/ensim/GUIResourceCustomize --role <**role**> --user <**username**> --url /static/xml/isp.dashboard.xml --skin <**skin_name**>--uri /tmp/isp.dashboard.xml

The resource is customized. To verify the results, log in to the Server Administrator control panel and refresh the Web page.

If you want to revert your changes, type the following command.

/usr/bin/ensim/GUIResourceRevert --role *<role>* --user *<username>* --url /static/xml/isp.dashboard.xml --skin *<skin_name>*

Customizing the font and color palette

To customize the font and color palette, you need to modify the **.css** file used by the administrative level. Each administrative level has its own **.css** file in the directory **/usr/lib/ensim/frontend/skins/<***skin_name***/css/.** The **.css** files in the directory are:

- **global.css**. Used to modify global style information common to all levels, for example, the styles used to display the *Log in* page.
- isp.global.css. Used to modify the style information on the Server Administrator control panel
- **reseller.global.css**. Used to modify the style information on the Reseller Administrator control panel
- site.global.css. Used to modify the style information on the Site Administrator control panel
- user.global.css.Used to modify the style information on the User Administrator control panel

The following procedure describes the steps to change the font color of a menu option in the left navigation bar.

▼ To customize the font color of a menu option in the left navigation bar:

- 1 Log in to the Server Administrator control panel.
- 2 Identify the class that contains the style configuration information for the left navigation bar.

To identify the class, drag the pointer to select a few menu options on the left navigation bar, right-click on the selected text, then select the option View Selection Source. The HTML source code is displayed.

In the HTML source code, locate the class that corresponds to the left navigation bar. The class name for the left navigation bar is **navbar-item**.

< a href="/isp/listservices" target="main">services<
/a>

- **3** Log in to the Ensim Pro server as the root user.
- 4 Verify that the resource /static/css/isp.global.css exists.

/usr/bin/ensim/GUIResourceList --role <*role>* --user <*username>* --url /static/css/isp.global.css --skin <*skin_name>*

5 Download the resource.

/usr/bin/ensim/GUIResourceDownload --role <role> --user <username> --url /static/css/isp.global.css --skin <skin_name> > /tmp/isp.global.css

6 Make the required changes to **/tmp/isp.global.css**. Locate the section that defines the style information for the left navigation

```
.navbar-item a, .navbar-item a:visited {
   text-transform: uppercase;
   padding-left:15px;
   padding-top:3px;
   padding-bottom:3px;
   display: block;
   text-decoration:none;
   color: #333333;
   background-image: url(/static/images/navbar-item-
   bullet1.gif);
   background-repeat: no-repeat;
   background-position: 2px center;
   cursor:hand;
   margin-right:10px;
```

- **7** Locate the attribute that defines the text color. In this example, locate the line color: #333333;
- **8** Update the style information as required and save the file.
- **9** Upload the resource to the Ensim Pro server.

/usr/bin/ensim/GUIResourceCustomize --role *<role>* --user *<username>* --url /static/css/isp.global.css --skin *<skin_name>*--uri /tmp/isp.global.css

The resource is customized. To verify the results, log in to the Server Administrator control panel and refresh the Web page.

If you want to revert your changes, type the following command.

/usr/bin/ensim/GUIResourceRevert --role <*role*> --user <*username>* --url /static/css/isp.global.css --skin <*skin_name>*

Customizing icons

You can replace the default Ensim Pro images with custom icons that suit your branding preferences. To replace an existing image, save the customized image using the file name of the original image, then replace the original image with the customized image. Make sure that the customized image is in the same graphic format as the original image. For example, do not copy a **.png** file as a **.gif** file.

For best results, make sure that the dimensions of the new image are the same as that of the original image as this will affect the visual appearance of the page.

▼ To customize icons:

- 1 Log in to the Ensim Pro server as the root user.
- **2** Assuming that the new image resides at **ftp://ftp.example.com/images/home/events_inbox.gif**, you can customize the **/static/images/email.gif** resource by typing the following command:

/usr/bin/ensim/GUIResourceCustomize --role *<role>* --user *<username>* --url /static/ images/email.gif --skin *<skin_name>* --uri ftp://ftp.example.com/images/home/events_inbox.gif

3 Refresh the Web page to view the change.

Relocating information panels on the left navigation bar

You can modify the default positioning of information panels on the left navigation bar by modifying the corresponding XSL style sheet. The following procedure provides instructions for relocating the **Login Info** panel.

▼ To relocate information panels on the left navigation bar:


- 1 Log in to the Ensim Pro server as the root user.
- 2 Verify that the resource /static/xsl/isp.navbar.xsl exists.

/usr/bin/ensim/GUIResourceList --role <*role*> --user <*username*> --url /static/xsl/isp.navbar.xsl --skin <*skin_name*>

3 Download the resource.

/usr/bin/ensim/GUIResourceDownload --role <*role*> --user <*username*> --url /static/xsl/isp.navbar.xsl --skin <*skin_name*> > /tmp/isp.navbar.xsl

4 Make the required changes to **/tmp/isp.navbar.xsl** as shown in the following figure and save the changes.





5 Upload the resource to the Ensim Pro server.

/usr/bin/ensim/GUIResourceCustomize --role *<role>* --user *<username>* --url /static/xsl/isp.navbar.xsl --skin *<skin_name>* --uri /tmp/isp.navbar.xsl

The resource is customized. To verify the results, log in to the Server Administrator control panel and refresh the Web page.

If you want to revert your changes, type the following command.

/usr/bin/ensim/GUIResourceRevert --role *<role>* --user *<username>* --url /static/xsl/isp.navbar.xsl --skin *<skin_name>*

Miscellaneous customizations

This section illustrates miscellaneous customizations you can perform on Ensim Pro. The section does not explicitly detail the customization process but uses graphical depictions to provide referential pointers to the files and classes you need to identify for customization.

Note: Some of the images used to illustrate the customizations exceed standard dimensions. These images are displayed in landscape mode in a separate section ("List of referenced images" on page 28).

For each of the following interface components, the illustration maps the various customizable elements to their corresponding HTML translation to facilitate easy identification of their classes and attributes. To customize, edit the XSL file that corresponds to the administrative level.


- **Top display bar.** See Customizing the top display bar (page **31**)
- Left navigation bar. See Customizing the left navigation bar (page 32)
- Top navigation bar. See Customizing the top navigation bar (page 33)
- **Dashboard.** See Customizing the dashboard (page 34)
- Forms. See Customizing the forms (page 35)
- Flip lists. See Customizing the flip lists (page 36)


APPENDIX A

List of referenced images

Adding links to the left navigation bar


Filename : isp.navbar.xml





Adding links in the shorcuts area


File: isp.dashboard.xml






Relocating shortcuts sections

File: isp.dashboard.xml





Customizing the top display bar



Notes :


* Server Administrator : The file isp.top.xs/ transforms the file isp.top.xm/ to generate the HTML output.

* Reseller Administrator : The file reseller.top.xsl transforms the file reseller.top.xml to generate the HTML output. * Site Administrator : The file siteadmin.top.xs/ transforms the file siteadmin.top.xm/ to generate the HTML output. * User Administrator : The file siteuser.top.xs/ transforms the file siteuser.top.xm/ to generate the HTML output.

Location of directory for XML files : [root] / static / xml Location of directory for XSL files : [root] / skins / [skin name] / xsl

Figure 8. Customizing the top display bar

Customizing the left navigation bar



Notes :

* Server Administrator : The file isp.navbar.xs/ transforms the file isp.navbar.xm/ to generate the HTML output.

* Reseller Administrator : The file reseller.navbar.xsi transforms the file reseller.navbar.xmi to generate the HTML output.
* Site Administrator : The file siteadmin.navbar.xsi transforms the file siteadmin.navbar.xmi to generate the HTML output.
* User Administrator : The file siteuser.navbar.xsi transforms the file siteuser.navbar.xmi to generate the HTML output.

Location of directory for XML files : [root] / static / xml Location of directory for XSL files : [root] / skins / [skin name] / xsl

Figure 9. Customizing the left navigation bar

Customizing the top navigation bar




Figure 10. Customizing the top navigation bar

Customizing the dashboard




Figure 11. Customizing the dashboard

Customizing the forms




Figure 12. Customizing the forms

Customizing the flip lists

				st-help-text-section"> Tiplist-help-title">Note
			<span class="1</th><th>liplist-help-text">Stop any service that you are not utilizing on this server.	
D				
View Subscribed Services				<div class="fliplist-action-bar"></div>
				 <div class="fliplist-button-container"></div>
Note				<pre><input class="button" name="add" type="submit" value="Add an Alias"/> </pre>
Stop any services that you are not utilizing on this server.				<div class="fliplist-search-bar"></div>
				Show: <select id="searchby" name="searchby"></select>
	ikasi Osmisa	a status		<option value="site">Site</option> <option value="ipaddress">IP Address</option>
Subscribed Services < <mark></mark>				
Add An Alias	Show: Name		Search Show All	<pre><input id="searchtext" name="searchtext" onkeypress="keyPressSearch(event.keyCode);" tabindex="1" type="text"/></pre>
Name <pre></pre>	sion	Status	Actions	<input <="" class="button" name="searchbutton" tabindex="2" td="" type="button"/>
				value="search" id="searchbutton"/>
Analog Web/FTP Log Analyzer	6.0			<input class="button" name="showall" showall"="" tabindex="3" type="button" value="show</td></tr><tr><td>DNS Server</td><td>9.2.4</td><td>di</td><td>/ 8 8 8</td><td>id="/>
		-		
OpenSSH Secure Shell <td>1></td> <td>e contra contra</td> <td>ê, e 🦉</td> <td>Note: This whole div is OPTIONAL. If you want to simply display a flip list without the</td>	1>	e contra	ê, e 🦉	Note: This whole div is OPTIONAL. If you want to simply display a flip list without the
Telnet	0.17	đ	e e e	search bar or buttons, then ignore the DIV.
POP3 + Imap Server	2004g	8	e e e	<pre>stable id="fliplist" name="fliplist" width="100%"> Fliplist <="fliplist" </pre>
				Table "
Apache Web Server		8		
Email	8.13.1	đ		<pre>{</pre>
			اه اه اه	
FTP	1.2.10	4		<select id="itemspp" name="itemspp"></select>
Power Tools				tems per page
				class="fliplist-pagenumbers" align="center">
OpenSSL Secure Web	0.9.7a			Page
10 items per page Page 1 of		-	14 A N	1
10 💽 items per page Page 1 of	3			 of
				<pre></pre>
Record Navig	ation Bar-	\sim		
				<ing id="pagefirst" name="pagefirst" src="/static/images/arrow_first_disabled.gif"></ing>
				<iring id="pageprev" name="pageprev" src="/static/images/arrow_prev_disabled.gif"> view exe="/static/images/arrow_prev_disabled.gif" id="pageprev" name="pageprev"></iring>
				
				<hr/>

Figure 13. Customizing the flip lists





