

# Ensim® Pro and Ensim Basic 4.0.3 for Linux® (ServerXchange®) Migration Guide

February 23, 2005

## Introduction

This guide provides information and instructions on migrating to Ensim® Pro and Ensim Basic 4.0.3 for Linux®. For simplicity, we refer to Ensim Pro and Ensim Basic 4.0.3 for Linux as “Ensim Control Panel” throughout the document.

### Note

The migration is platform-independent. Irrespective of the current operating platform of your Ensim Control Panel server, you can migrate from version **4.0.1** and version **4.0.2** to any supported platform—Fedora Core 1, Fedora Core 2.

Topics in this guide include:

- [“About the migration” on page 1](#)
- [“System requirements” on page 2](#)
- [“Migrating to the latest version of Ensim Control Panel” on page 2](#)
- [“Feedback and support” on page 3](#)
- [“Legal and copyright notice” on page 3](#)

## About the migration

You can migrate to Ensim Control Panel 4.0.3 from version 4.0.1 and version 4.0.2.

Migration is a two-step process that requires you to:

- Back up data on your Ensim Control Panel server  
Sites hosted on Ensim Control Panel will be inaccessible when the backup is in progress. This could typically range from a few minutes to a few hours depending on the number of sites hosted on the server.
- Restore the data on a server running Ensim Control Panel 4.0.3

---

## System requirements

Before you migrate, you must install Ensim Control Panel 4.0.3 on the server to which you want to migrate data.

### Important

Please note the version of the base file system (BFS) that must be installed on the server to which you migrate.

**Fedora Core 1:** Ensim Control Panel 4.0.3 requires **BFS 01-13** to be installed on your Private and Dedicated servers. Once you install BFS 01-13 on your Private and Dedicated servers, you **cannot** install earlier versions of Ensim Control Panel on them.

**Fedora Core 2:** Ensim Control Panel 4.0.3 requires **BFS 02-3** to be installed on your Dedicated servers. The release does **not** support installation of Ensim Control Panel 4.0.3 on Private servers.

---

For information on installation requirements and instructions, please refer to the document *Ensim Pro and Ensim Basic 4.0.3 for Linux (ServerXchange) Installation Guide* available at <http://www.ensim.com/support/sxc/index.shtml>.

## Migrating to the latest version of Ensim Control Panel

The following section provides instructions on migrating to the latest version of Ensim Control Panel. Please review the section “[System requirements](#)” on page 2 before you migrate data.

### Procedure

To migrate to the latest version of Ensim Control Panel:

- 1 Log on to the Appliance Administrator control panel on the Ensim Control Panel server from which you want to migrate data.
- 2 Back up the data on the server.
  - a In the shortcuts section of the Home page, click **Backup/Restore** (Tools section).
  - b Click **Backup** (if not already selected). The *Backup* form opens.
  - c Perform an **appliance** backup. For instructions on backing up data, please refer to the online Help *Appliance Administrator online Help* (**Book:** Backing up and restoring data)
- 3 Log on to the Appliance Administrator control panel on the server on which you installed Ensim Control Panel 4.0.3.
- 4 Restore the data on the server.
  - a In the shortcuts section of the Home page, click **Backup/Restore** (Tools section).
  - b Click **Restore**. The *Restore* form opens.
  - c Restore the data. For instructions on restoring data, please refer to the online Help *Appliance Administrator online Help* (**Book:** Restoring archived data)

---

## Feedback and support

To take advantage of Ensim's support services or to find additional product documentation, visit the Ensim support site, <http://support.ensim.com>.

To log in to Ensim online support, go to <https://onlinesupport.ensim.com>.

To provide feedback about Ensim products or documentation, please use the feedback form at <http://www.ensim.com/about/feedback.asp>.

## Legal and copyright notice

This document contains information proprietary to Ensim Corporation and its receipt or possession does not convey any rights to reproduce, disclose, manufacture, or sell anything it might describe. Reproduction, disclosure, or use without Ensim's specific written authorization is strictly forbidden.

Ensim Corporation makes no representations or warranties with respect to the content or use of this document. It also reserves the right to revise this document at any time without the obligation to notify any person of such revision.

Ensim, the Ensim logo, and ServerXchange are registered trademarks of Ensim Corporation.

All other trademarks and copyrights are the property of their respective owners.

© 2005 Ensim Corporation. All rights reserved.